2021

Immutable Backup Repository OVA

A Virtual Appliance designed for mounting iSCSI LUN as Veeam Immutable Backup Repository

JOHN BORHEK



Contents

Introduction	.2
Creating a LUN on Your iSCSI SAN	3
Import the OVA	.3
Powering on and Configuring the Immutable Repository VM	.4
Configuring Your Immutable Repository in Veeam Backup and Replication 11	12
Additional Measures	22
References	22



Introduction

Veeam Backup and Replication 11 is a true game-changer with its Immutable Backup feature. Moving forward, Veeam Immutable Backups will free organizations from the hassle of physical tape libraries as well as eliminating the need for expensive "virtual tape libraries," all while providing easily manageable backup chains.

Veeam Immutable Backups are the equivalent of "air gapped," tape, or WORM backups! Immutable Backups are accomplished through the use of a Linux repository server, the XFS filesystem (to support Fast Clone), one-time-use credentials, and the immutability flag which is a property of just about any Linux filesystem.

What about validation? Does it actually work, you ask? Yes! And it is tested and proven by <u>Cohasset Associates</u> meeting the requirements for non-rewritable, non-erasable storage as specified by SEC 17a-4(f), FINRA 4511(c) and CFTC 1.31(c)-(d).

What an Immutable Repository is designed to do:

- Protect your backups from unintentional encryption by Ransomware
- Prevent backup file deletion by unauthorized administrators.

What an Immutable Repository cannot do:

- Prevent deletion of the SAN LUN by users who have SAN administrator credentials
- Prevent formatting of the volume by users who have login credentials for the Immutable Repository VM.

As a Best Practice, Veeam recommends that Immutable Repositories be deployed on a physical server with lots of disk space, such as an HPE Apollo. While that's an admirable goal, there are lots of us with Virtualized and Cloud Infrastructures, and we rely on SAN systems to provide block storage.

VMsources' goal has been to create a Virtual Appliance in OVA format, following Veeam Best Practices, making it easy for anybody to mount an iSCSI LUN as a Veeam Immutable Repository. Not everybody is fond of Linux or the CLI, so we have created an Ubuntu 20.04LTS server with all of the requirements baked-in as an OVA Virtual Appliance, and then documented the step-by-step instructions to mounting a SAN LUN, formatting it as XFS, and then creating your Veeam Immutable Repository.

PLEASE NOTE: **This Virtual Appliance is provided without warranty of any kind.** You must change the passwords to very strong, disable SSH, and the VM must run on secure, firewalled networks in order for any of this to amount to a hill of beans.

Download the appliance: <u>https://www.johnborhek.com/download/immutable-repository-for-veeam-backup-and-replication-11/</u>



Creating a LUN on Your iSCSI SAN

- 1. Create a LUN on your iSCSI SAN
 - Most likely, your iSCSI SAN will require you to map the IQN of the initiator (the Immutable Repository) to the LUN which you have carved out. The Immutable Repository IQN is: iqn.2008-05.com.vmsources.immutable-repo:01
 - b. The IQN can be configured by editing: /etc/iscsi/initiatorname.iscsi

Import the OVA

- 1. Import the Immutable Repository OVA to your VMware vSphere environment.
 - a. Locate the OVA package and click Next.

Deploy OVF Template	Select an OVF template	×
1 Select an OVF template	Select an OVF template from remote URL or local file system Enter a URL to download and install the OVF package from the Internet, or browse to a location accessible from your computer, such as a local hard drive, a network share, or a CD/DVD drive.	
2 Select a name and folder	OURL	
3 Select a compute resource	http https://remoteserver-address/filetodeploy.ovf .ova	-
4 Review details	Local file	Ċ
5 Select storage	UPLOAD FILES immutable-rep- ova	
6 Ready to complete		
	CANCEL	\supset

b. This is expected when importing an OVA. Click Next.

Deploy OVF Template	Review details Verify the template details.		×		
1 Select an OVF template	▲ The OVF package contains advanced configuration options, which might pose a security risk. Review the advanced configuration options below. Click next to accept the advanced configuration options.				
2 Select a name and folder					
3 Select a compute resource	Publisher	No certificate present			
· · · · ·	Download size	1.5 GB			
4 Review details	Size on disk	3.5 GB (thin provisioned) 40.0 GB (thick provisioned)			
5 Select storage 6 Select networks	Extra configuration	virtualHW.productCompatibility = hosted nvram = immutable-repo.nvram			
7 Ready to complete			_		
1000 100/10 server		CANCEL BACK NEXT	ight angle		



c. Map your networking and click Next.

Deploy OVF Template	Select networks Select a destination network for each source network.	×
1 Select an OVF template	Source Network	
2 Select a name and folder	Source Network	Veeam ~
3 Select a compute resource	hostonly	iscsi 🗸
4 Review details		2 items
5 Select storage	IP Allocation Settings	\sim
6 Select networks	IP allocation:	Static - Manual
7 Ready to complete	IP protocol:	IPv4
		CANCEL BACK NEXT

- i. Place the Source Network 'nat' on the same network as your Veeam Servers
- ii. Place the Source Network 'hostonly' on the same network as your iSCSI target ports

Powering on and Configuring the Immutable Repository VM The initial password for both root and administrator is: P@ssw0rd (That's a zero in P@ssw0rd)

- 1. Power on immutable-repo VM
- 2. Open VMRC to immutable-repo VM and log on as root (possible because you're using the console).

A immutable-repo2 - VMware Remote Console	immutable-repo2 - VMware Remote Console						
⊻MRC ▼ ▼ 母 □							
Ubuntu 20.04.2 LTS immutable–repo tty1							
immutable-repo login: root Password: Welcome to Ubuntu 20.04.2 LTS (GNU/Linux 5.4.0–70–generic x86_64)							
<pre>* Documentation: https://help.ubuntu.com * Management: https://landscape.canonical.com * Support: https://ubuntu.com/advantage</pre>							
System information as of Tue 13 Apr 2021 05:41:23 PM UTC							
System load: 0.95 Users logged in: 0 Usage of /: 33.1% of 19.56GB IPv4 address for ens32: 192.168.158.40 Memory usage: 4% IPv4 address for ens32: 192.168.99.131 Swap usage: 0% IPv4 address for ens35: 192.168.89.244 Processes: 256 IPv4 address for ens35: 192.168.89.244							
* Introducing self-healing high availability clusters in MicroK8s. Simple, hardened, Kubernetes for production, from RaspberryPi to DC.							
https://microk8s.io/high–availability							
8 updates can be installed immediately. 8 of these updates are security updates. To see these additional updates run: apt list ––upgradable							
Last login: Tue Apr 13 14:05:36 UTC 2021 on tty1 root@immutable-repo:~# _							



3. Change root and vbruser password (HINT: use a randomized long password that is not used on any other system and store this password securely and offline). NOTE: the username "vbruser" is arbitrary and can be changed as needed. There is only a requirement for an un-privileged user that has ownership rights to the Immutable Repository folder (Later)

passwd root passwd vbruser

7	immutable-repo2 - VMware Remote Console	
VMRC 🕶 📕 👻 🔂		
root@immutable–repo:~# passwo	l root	
New password: Retype new password:		
passwd: password updated succ		
root@immutable–repo:~# passwo New password:	l administrator	
Retype new password:		
passwd: password updated succ root@immutable-repo:~# _	cessfully	

4. Change the Netplan network config to suit your environment. You can use the /etc/netplan/50immutable-init.yaml as a template and modify the variables (in white). Be careful, indentation is important in this file, follow the example.

vi /etc/netplan/50-immutable-init.yaml

- i. ens32 is your Veeam/Management Network. It will require an IP address, gateway and nameservers. Modify the values in white.
- ii. ens35 is your iSCSI network. In most cases a gateway is not required or even desirable on your iSCSI/SAN network. Modify the values in white.
- iii. If Jumbo Frames are not wanted, remove the MTU line

```
# This is the network config written by 'subiquity'
network:
  ethernets:
    ens32:
            addresses:
               - 192.168.158.40/24
            gateway4: 192.168.158.2
            nameservers
                    search: [mydomain, otherdomain]
                    addresses: [8.8.8.8, 8.8.4.4]
            dhcp4: true
    ens35:
      addresses:
               - 192.168.89.244/24
      mtu: 9000
  version: 2
```



b. Run the command:

netplan apply

- i. If it returns an error, most likely indentation is off. Go back and look for mistakes.
- 5. Now, let's ping our Veeam server and iSCSI Target to make sure networking is correct.
 - a. Run the command: ping -c 4 <IP of Veeam>
 - b. Run the command: ping -c 4 -d -s 8972 <IP of ISCSI Target>
 - c. If all pings are returned, you are configured correctly.
 - d. If the iSCSI ping does not return, remove: mtu: 9000 from Netplan
 - i. Run: netplan apply again.

immutable-repo - VMware Remote Console	
root@immutable-repo:~# ping -c 4 172.31.0.79 PING 172.31.0.79 (172.31.0.79) 56(84) bytes of data. 64 bytes from 172.31.0.79: icmp_seq=1 ttl=127 time=0.624 ms 64 bytes from 172.31.0.79: icmp_seq=2 ttl=127 time=0.576 ms 64 bytes from 172.31.0.79: icmp_seq=3 ttl=127 time=0.631 ms 64 bytes from 172.31.0.79: icmp_seq=4 ttl=127 time=0.669 ms	
172.31.0.79 ping statistics 4 packets transmitted, 4 received, 0% packet loss, time 3068ms rtt min/avg/max/mdev = 0.576/0.625/0.669/0.033 ms root@immutable-repo:~# ping -c 4 -d -s 8972 192.168.89.2 PING 192.168.89.2 (192.168.89.2) 8972(9000) bytes of data. 8980 bytes from 192.168.89.2: icmp_seq=1 ttl=64 time=3.19 ms 8980 bytes from 192.168.89.2: icmp_seq=2 ttl=64 time=1.60 ms 8980 bytes from 192.168.89.2: icmp_seq=3 ttl=64 time=1.50 ms 8980 bytes from 192.168.89.2: icmp_seq=4 ttl=64 time=2.86 ms	
192.168.89.2 ping statistics 4 packets transmitted, 4 received, 0% packet loss, time 3005ms rtt min/avg/max/mdev = 1.499/2.286/3.192/0.748 ms root@immutable-repo:~#	

- 6. At this point, you can log on using ssh or continue to use the VMRC console. ssh is convenient as it will allow you to copy and paste the required commands to get started. To login with ssh:
 - a. Start by logging on as the user: administrator
 - i. Use the password you just assigned to the administrator user
 - b. Then execute: su
 - i. Use the password you assigned to root



7. Now, configure your iSCSI Target by running the commands, one line at a time:

iscsiadm -m discovery -t sendtargets -p <iSCSI Target IP> iscsiadm -m node -o show iscsiadm -m node --op=update -n node.conn[0].startup -v automatic iscsiadm -m node --op=update -n node.startup -v automatic iscsiadm -m node --loginall=automatic (requires time) systemctl enable open-iscsi systemctl enable iscsid systemctl restart iscsid.service iscsiadm -m session -o show



8. Find your volume by running the command:

fdisk -l

root@immutable-repo: ~ Disk /dev/mapper/ubuntu--vg-ubuntu--lv: 20 GiB, 21474836480 bytes, 41943040 sectors Units: sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes Disk /dev/sdb: 1.88 TiB, 2048000000000 bytes, 4000000000 sectors Disk model: DH3000 Units: sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 1048576 bytes Disk /dev/sdc: 1.88 TiB, 2048000000000 bytes, 4000000000 sectors Disk model: DH3000 Units: sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 1048576 bytes Disk /dev/sdd: 1.88 TiB, 2048000000000 bytes, 4000000000 sectors Disk model: DH3000 Units: sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 1048576 bytes Disk /dev/sde: 1.88 TiB, 2048000000000 bytes, 4000000000 sectors Disk model: DH3000 Units: sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 1048576 bytes Disk /dev/mapper/mpatha: 1.88 TiB, 2048000000000 bytes, 4000000000 sectors Units: sectors of 1 * 512 = 512 bytes Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 1048576 bytes oot@immutable-repo.~#

Your device will either be identified by: /dev/sdb (if there is only one target with one path, or by: /dev/mapper/mpatha (if it is a multipath iSCSI SAN). You will want to use multipath (mpath) if available.



9. Once you have identified your volume, format it with this command with /dev/sdb or /dev/mapper/mpatha as appropriate (takes a bit):

mkfs.xfs -b size=4096 -m reflink=1,crc=1 /dev/mapper/mpatha

🛃 root@	immutable-repo: ~		
root@imm	<pre>nutable-repo:~# mkfs.xfs</pre>	-b size=4096	-m reflink=1,crc=1 /dev/mapper/mpatha
meta-dat	a=/dev/mapper/mpatha	isize=512	agcount=4, agsize=125000000 blks
		sectsz=512	attr=2, projid32bit=1
		crc=1	<pre>finobt=1, sparse=1, rmapbt=0</pre>
		reflink=1	
data		bsize=4096	blocks=500000000, imaxpct=5
		sunit=0	swidth=0 blks
naming	=version 2	bsize=4096	ascii-ci=0, ftype=1
log	=internal log	bsize=4096	blocks=244140, version=2
		sectsz=512	<pre>sunit=0 blks, lazy-count=1</pre>
realtime	e =none	extsz=4096	blocks=0, rtextents=0
root@imm	utable-repo:~#		

10. Identify the UUID of the volume:

blkid

root@immu	table-repo:~# blkid
	: UUID="168abb7c-082c-49b5-a158-2f4b38d2c934" TYPE="ext4" PARTUUID="7b4d2480-529b-4485-8270-3
	: UUID="p10Mh4-AJdQ-cGAe-p1vH-F7qU-N5N7-FXAo6b" TYPE="LVM2_member" PARTUUID="9c971828-783b-42
	er/ubuntuvg-ubuntulv: UUID="e1ced7da-7d08-428d-af55-1cc0f538d7b0" TYPE="ext4"
· · ·	0: TYPE="squashfs"
· · · · ·	1: TYPE="squashfs"
· · ·	2: TYPE="squashfs"
/dev/loop	3: TYPE="squashfs"
· · · ·	4: TYPE="squashfs"
	5: TYPE="squashfs"
	: PARTUUID="176c3ced=7907=450d=8e4a=607172aa7463"
/dev/mapp	er/mpatha: UUID="8b28df99-a2fe-4012-b5f3-cefbe881e47d" TYPE="xfs"
root@immu	table-repo:-#

11. Copy the UUID of the xfs volume to a text file, but remove the quotations for use later:

UUID=8b28df99-a2fe-4012-b5f3-cefbe881e47d

12. Your Immutable Repository mount point is pre-configured and ready-to-go with the correct ownership and user permissions pre-assigned as:

/mnt/immutable-repo-01



13. OPTIONAL: Step 13 is entirely optional as there is a pre-configured user and mount-point. If you wish to create additional vbrusers and repositories using this server, add additional users and mount points using these commands:

adduser newvbrusername
usermod -aG sudo newvbrusername
mkdir /mnt/newvbrreponame
chown -R newvbrusername: newvbrusername /mnt/newvbrreponame
chmod -R 700 /mnt/newvbrreponame

14. Edit /etc/fstab and substitute your UID and mount point (pre-configured mount point is /mnt/immutable-repo-01) for the values shown in the example:

Proot@immutable-repo: ~
<pre># /etc/fstab: static file system information.</pre>
<pre># # Use 'blkid' to print the universally unique identifier for a # device; this may be used with UUID= as a more robust way to name devices # that works even if disks are added and removed. See fstab(5). #</pre>
<pre># <file system=""> <mount point=""> <type> <options> <dump> <pass> # / was on /dev/ubuntu-vg/ubuntu-lv during curtin installation /dev/disk/by-id/dm-uuid-LVM-z30mgX7RMC0w6PWK4Z1C7DRuk04LDsAxvNeDQ7nA7YIOwR0qWsyho8Bg06HZj793 / ext4 defaults 0 0 # /boot was on /dev/sda2 during curtin installation /dev/disk/bv-uuid/168abb7c-082c-49b5-a158-2f4b38d2c934 /boot ext4 defaults 0 0</pass></dump></options></type></mount></file></pre>
/swap.img none swap sw 0 0
UUID=8b28df99-a2fe-4012-b5f3-cefbe881e47d /mnt/immutable-cloud099 xfs nosuid,nodev,nofail,x-gvfs-show 0 0
/mnt/immutable-repo-01

a. Add this line, substituting your UUID :

UUID=8b28df99-a2fe-4012-b5f3-cefbe881e47d /mnt/immutable-repo-01 xfs
nosuid,nodev,nofail,x-gvfs-show 0 0

15. Reboot!

vi /etc/fstab




- 16. Login as "root" using the VMRC.
- 17. Verify that your volume automounted to the correct path with the command
 - df -h

_					
📌 im	immutable-repo2 - VMware Remote Console				
root@immutable–repo:~# df –h					
Filesystem	Size	Used	Avail	Use%	Mounted on
udev	3.9G	0	3.9G	0%	/dev
tmpfs	794M	1.5M	792M	1%	/run
/dev/mapper/ubuntuvg-ubuntulv	20G	7.0G	12G	38%	
tmpfs	3.9G	0	3.9G	0%	/dev/shm
tmpfs	5.OM	0	5.OM	0%	/run/lock
tmpfs	3.9G	0	3.9G	0%	/sys/fs/cgroup
/dev/sda2	976M	200M	710M	22%	/boot
/dev/loop2	70M	70M	0	100%	/snap/lxd/19188
/dev/loop0	56M	56M	0	100%	/snap/core18/1997
/dev/loop3	33M	33M	0	100%	/snap/snapd/11402
/dev/loop1	56M	56M	0	100%	/snap/core18/1944
/dev/loop5	33M	33M	0		/snap/snapd/11588
/dev/loop4	71M	71M	Ô		/snap/1xd/19647
/dev/mapper/mpatha	1.9T	14G	1.9T	1%	/mnt/immutable-cloud099
tmpfs	794M	Û	794M		/run/user/0
root@immutable–repo:~# _				/	
/mnt/immutable-repo-01					



Configuring Your Immutable Repository in Veeam Backup and Replication 11

1. Now configure your Veeam Immutable Repository in Veeam Backup and Replication 11.




2. Now choose Linux.

	3,
Adds local server storage presented as a regular volume or Storage Spaces. For better performance and storage efficiency, we recommend using ReFS.	
Adds local server storage, or locally mounted NFS share. The Linux server must use bash shell, and have SSH and Perlimstalled.	
Cancel	



3. Give your repository and name and click Next.



4. Now you need to click on Add New so you can assign a repository.

New Backup Repository				×
Server Choose repository serv	ver. You can select server from the list of managed servers add	ed to the console.		
Name	<u>R</u> epository server:		~	Add New
Server				
Repository	Path	Capacity	Free	Populate
Mount Server				
Review				
Apply				
Summary				
	< <u>P</u> revious	<u>N</u> ext >	Einish	Cancel



a. Enter the FQDN or IP of your Immutable Repository VM and click Next.

New Linux Server	×
Specify DNS name or Name	IP address of Linux server. The server must have SSH and Perl installed.
Name SSH Connection	DNS name or IR address: 192.168.99.99 Description:
Review	Created by CLOUD/John at 4/14/2021 8:08 AM.
Apply Summary	
	< Previous Next > Einish Cancel

b. Now add your SSH connection.

New Linux Server		×	
SSH Connection Provide credentials fo	r service console connection, and adjust secure shell (SSH) port number using advanced settings if	required.	
Name	Credentials:		
SSH Connection Review Apply Summary	Manage accounts	Add Linux acco Linux privat Single-use	
	Customize advanced connection settings, such as SSH and data mover ports	Advanced	
	< Previous Next > Finish	Cancel	

c. You will use the 'vbruser' user credentials in Veeam. At this point, you still have root access and could 'Use "su" if "sudo" fails', however you shouldn't have to choose this. Choose only: Elevate



account privileges automatically.

Credentials	×
Username: administrator Password: ••••••• SSH port: 22	•
Non-root account	
 Elevate account privileges automatically Add account to the sudoers file Use "su" if "sudo" fails Root password: 	
Description:	
administrator	
<u>O</u> K <u>C</u> ancel	

d. We just created it. Click Yes.





e. Review your choices and click Apply.

New Linux Server	×
Review Please review your settings and click Apply to continue.	
Name Due to these modifications the following	omponents will be installed or removed on the target host:
SSH Connection	Status
Iransport	will be installed
Review	
Apply	
Summary	
A fact on the fact of the second seco	20 be testelled as the tesset back
After you click Apply missed components	III be installed on the target host.
	< <u>Previous</u> App <u>ly</u> Einish Cancel

f. After it's finished, click on Next.

New Linux Server		×
Apply Please wait whil	e required operations are being performed, this may take a few minu	tes.
Name	Message	Durat
	Starting infrastructure item update process	0:00:03
SSH Connection	Checking if Veeam Data Mover service is supported by	0:00:01
Review	Oiscovering existing Veeam Data Mover service	
	Installing Veeam Data Mover service	0:00:13
Apply	Discovering existing Veeam Data Mover service	
Summary	Setting server certificate	0:00:01
Summary	Resolving server certificate thumbprint	
	Setting client certificate	0:00:01
	Configuring Veeam Data Mover service	
	Restarting Veeam Data Mover service	
	Testing Veeam Data Mover service connection	0:00:01
	Collecting hardware info	0:00:03
	Creating database records for server	
	C Linux server saved successfully	
	< Previous	Next > Einish Cancel



g. Check out the summary and then click Finish.

New Linux Server		×
You can copy the conf	iguration information below for future reference.	
Name SSH Connection Review Apply Summary	Summary: Linux host '192.168.99.99' was successfully created. SSH options: Credentials type: Single-use User: administrator Elevate account to the sudders file: no Use 'su' if 'suddo' fails: no Hardware info: Chassis type: Virtual (VMware) Cores count: 4 Components: Transport using port 6162	
	< Previous Next > Einish Cancel	

h. Now we need a repository server. Click on Add New.


New Backup Repository						×
Server Choose repositor	ry server. You can select se	rver from the list of managed	servers added to	the console.		
Name	Repository server:					\frown
Server	192.168.99.99 (Cre	eated by CLOUD\john at 4/14/	2021 8:08 AM.)		~	Add New
Repository	Path	^		Capacity	Free	Populate
Mount Server						
Review						
Apply						
Summary						
		<	Previous	<u>N</u> ext >	<u>F</u> inish	Cancel



i. Do the following steps to configure:


	Edit Backup Repository	X
	Repository Type in path to the fold	der where backup files should be stored, and set repository load control options.
/mnt/immutable-repo-01 —	Name Servar Repository Mount Server Review Apply Summary	Patr to folder: //mnt/recovery //mnt/recovery Populate Capacity: <unknown> Free space: <unknown> ✓ se fast cloning on XFS volumes (recommended) Reduces storage consumption and improves synthetic backup performance. ✓ ake recent backups immutable for: ? ✓ ake recent backups immutable for: ? ✓ ake recent backups from modification or deletion by ransomware or hackers. GFS full backups are made immutable for the entire duration of their retention policy. Load control Running too many concurrent tasks against the repository may reduce overall performance, and cause I/O timeouts Control dtorage device saturation with the following settings: ✓ Limit maximum concurrent tasks to: 4 ✓ Limit read and write gata rate to: 1 1 MB/s</unknown></unknown>
		Click Advanced to customize repository settings.
		< <u>Previous</u> <u>N</u> ext > <u>Finish</u> Cancel

i. Click Browse, and Locate the /mnt/immutable-repo-01 folder (or folder you created in Step 13) and click OK.





- ii. Click on Advanced:
 - 1. Align backup file data blocks
 - 2. Use per-machine backup files



- iii. Use Fast cloning on XFS....
- iv. Make recent backups immutable for.... (set your desired number)
- v. Set "Limit maximum concurrent tasks to" equal to the number of vCPUs which you assigned the repository VM

j. Choose a write cache folder and click Next.

New Backu	ip Repository	×
	Mount Server Specify a server to mount backups to when performing advanced restores (file, application item and instant VM recoveries). In recoveries require a write cache folder to store changed disk blocks in.	ıstant
Name Server Repositor	Instant recovery write cache folder	ld New
1.1	E:\ProgramData\Veeam\Backup\IRCache\ BI	rowse
Mount Se	rver Ensure that the selected volume mis sufficient free disk space to store changed disk blocks of instantly recovered VMs. We recommend placing write cache on an SSD drive.	1
Apply		P <u>o</u> rts
Summary	Unlocks instant recovery of any bacupu (physical, virtual or cloud) to a VMware vSphere VM. vPow service is not used for instant recovery to a Microsoft Hyper-V VM.	rer NFS
	< <u>Previous</u> <u>Next</u> > <u>Finish</u> C	Cancel



k. Review your choices and click Apply.

New Backup Repository		×
Review Please review the setti	ings, and click Apply to continue.	
Name	The following components will be processed on server cloud0	01-vbr-01.cloud.vmsources.com:
	Component name	Status
Server	Transport	already exists
Repository	vPower NFS	already exists
	Mount Server	already exists
Mount Server		
Review		
Apply		
Summary		
	_	
	Search the repository for existing <u>b</u> ackups and import ther	n automatically
	Import guest file system index data to the catalog	
	< Previous	App <u>ly</u> Einish Cancel

I. After it's finished doing its thing, click Next.

New Backup Repository			Х
Apply Please wait while	backup repository is created and saved in configuration, this may ta	ke a few minutes.	
Name	Message Starting infrastructure item update process	Durat 0:00:03	
Server	 Starting infrastructure item update process [cloud001-vbr-01] Discovering installed packages 	0:00:04	
Repository	[cloud001-vbr-01] Registering client CLOUD001-VBR-0		
Mount Server	 [Cloud001-vbr-01] Registering client CLOUD001-VBR-0 [Cloud001-vbr-01] Registering client CLOUD001-VBR-0 		
Review	[cloud001-vbr-01] Discovering installed packages		
Apply	 All required packages have been successfully installed Detecting server configuration 		
Summary	Reconfiguring vPower NFS service Creating configuration database records for installed p Collecting backup repository info		
	Creating database records for repository	0:00:09	
	Backup repository has been added successfully		
	< <u>P</u> revious	Next > Einish Cancel	



m. Nothing left to do but click Finish!

New Backup Repository		\times
You can copy the cont	iguration information below for future reference.	
Name Server Repository Mount Server Review Apply Summary	Summary: Linux backup repository 'Immutable Repository' was successfully created. Mount host: cloud001-vbr-01.cloud.vmsources.com Backup folder: /mnt/immutable-cloud099 Write throughput unlimited Max parallel tasks: 4 Fast cloning on XFS volumes: disabled Days of immutability: disabled	
	< <u>Previous</u> Next > Einish Cancel	



VMsources Group, Inc. www.vmsources.com 1-866-644-7764

Additional Measures

Configure SSH to use two-factor authentication

https://ubuntu.com/tutorials/configure-ssh-2fa#1-overview

References

https://ubuntu.com/server/docs/service-iscsi

https://netplan.io/examples/

https://www.veeam.com/blog/v11-immutable-backup-storage.html